



MJ'S VETEÖL | 20 LITER

WHEAT BEER



Veteöl from MJ's Bryggeri is a tribute to the sunny days in Karlstad, Sweden. A well balanced beer with fruit, citrus and classic wheat beer flavors and aromas.

KIT CONTENT:

MALT:

2,50 kg Wheat Malt
1,90 kg Pilsner Malt
0,20 kg Caramel Pale Malt

HOPS:

10 g Mosaic
16 g Mosaic
30 g Mosaic

YEAST:

2 pcs Munich Classic

EXPECTED OG: 1.051

EXPECTED FG: 1.015

EXPECTED ABV: 4.7%%

FERMENTATION TEMP: 20°C

BEER XML: File for Brewfather etc available for download at maltmagnus.se

IF YOU HAVE BREWED BEFORE:

This is basic step-by-step instructions mainly for beginners. If you have brewed before, just use your brewing equipment as usual. You will find mash temperatures and hop additions steps in these instructions.

YOU NEED:

- Cleaner and sanitizer
- Kettle or brewing equipment to boil 25-29 liters of wort.
- Kettle for heating sparge water.
- All Grain brewing equipment.
- Fermentation equipment.
- Bottling or kegging equipment.

Equipment and ingredients can be found at www.maltmagnus.se

BREW DAY

1. Start with making sure everything in the kit is included.
2. Read through the instructions!
3. Wash and clean the brewing equipment. Do not use the same equipment used while cooking or washing up.
4. Sterilize the equipment that will be in contact with the wort after chilling. Follow the dosage instructions on your sanitizer. Your beer can get infected if this step is not done correct.

STEP 1

1. Fill up with water to the false bottom if you have one before measuring 3 liters per 1 kg malt.
2. Heat 3 liters of water per 1 kg malt to +65°C.

STEP 2

MASH IN - Add the crushed malt while stirring to avoid lumps. Mash for 60 minutes.

STEP 3

MASH OUT - Rise the temperature while stirring to +76°C for about 10 minutes.

STEP 4

SPARGE - Prepare water in your hot liquor tank / kettle to a temperature of +80°C.

Rinse the malt gently with the hot water until you reach a total volume of 23-25 liters in your boil kettle.

STEP 5

BOIL - Start heating until you reach a boil.

The hops shall boil for 70 minutes. Do not use lid!

Open the bag labeled **16 g Mosaic**. Pour the content into the kettle. Boil for 60 minutes.

Open the bag labeled **10 g Mosaic**. Pour the content into the kettle. Boil for 10 minutes.

Turn off the heat / Flame out!

Open the bag labeled **30 g Simcoe**. Pour the content into the kettle. Stir for a few minutes.

STEP 6

COOLING – Cool the wort as rapidly as possible to around +20°C. Use spiral cooler or other cooling equipment. If you do not have any, put the fermentation bucket in a cool water bath.

NOTE! Do not use any un-sanitized equipment or hands in the wort at this point!

Take a sample and measure the Oeschle value with a hydrometer and write down the result. This is the OG value.

STEP 7

FERMENTATION – Open up the yeast package with a sterilized scissors and pour it into the cooled wort.

Fill the airlock and put it into the lid of the fermentation bucket.

Place the bucket on a dark spot keeping a temperature of +20°C. The fermentation is normally done within 2-7 days, but let it be for 14 days.

When the fermentation is done take a wort sample and measure it with your hydrometer. This is the FG.

Calculation ABV: $(OG-FG) \times 131,25 = ABV$

BOTTLING

BOTTLING YOUR BEER:

1. Wash and sanitize the bottles. Put the caps in a bowl with sanitizer.
2. We recommend **Carbonation Drops**. Follow the dosage instructions on the package. You can also use regular table sugar: 2-3 grams per 33 cl bottle.
3. Fill the bottles with beer and leave a airpocket at the top. Cap it and place it in room temperature for at least one week. Open a bottle and test the carbonation levels. If you think its enough, chill for a week or two. Enjoy!