



# OKTOBERFEST | 20 LITER

## LAGER



Malty is the word that describe the taste of this beer. Light to medium body with caramel and toffee flavors. You will also find notes of dried fruit. Oktoberfest Lager has a well balanced bitterness and a wonderful orange color similar to autumn leaves.

### KIT CONTENT:

#### CRUSHED MALT:

2,8 kg Pilsner Malt | Svensk  
1,32 kg Light Munich Malt  
0,56 kg Dark Munich Malt  
0,40 kg Caramel Malt 100  
0,24 kg Victory

#### HOPS:

35 g Perle

#### YEAST:

1 st Bavarian Lager | Wyeast 2206

**EXPECTED OG:** 1.050

**FERMENTATION TEMP:** 8-14°C

#### ALREADY A SKILLED HOME BREWER:

Use your regular brewing equipment and brewing method. Time and temperatures can be found in this instructions.

### YOU NEED:

- ◆ Cleaner and sanitizer
- ◆ Kettle or brewing equipment to boil 25-29 liters of wort.
- ◆ Kettle for heating sparge water.
- ◆ All Grain brewing equipment.
- ◆ Fermentation equipment.
- ◆ Bottling or keggng equipment.

Equipment and ingredients can be found at [www.maltmagnus.se](http://www.maltmagnus.se)

## BREW DAY

Start with making sure everything in the kit is included.

Read through the instructions!

Take the yeast package out of the fridge.

Wash and clean the brewing equipment. Do not use the same equipment used while cooking or washing up.

Sterilize the equipment that will be in contact with the wort after chilling. Follow the dosage instructions on your sanitizer. Your beer can get infected if this step is not done correct.

## STEP 1

Heat 3 liters of water per 1 kg malt to +67°C. Fill up with water to the false bottom if you have one before measuring 3 liters per 1 kg malt.

## STEP 2

**MASH IN** - Add the crushed malt while stirring. The temperature will now cool down a bit. Start heating again while stirring until you reach the correct temperature again. Turn off the heat and put a lid on. Let rest for 60 minutes.

## STEP 3

**MASH OUT** - Rise the temperature while stirring to +76°C for about 10 minutes.

## STEP 4

**SPARGE** - Prepare water in your hot liquor tank / kettle to a temperature of +80°C.

Rinse the malt gently with the hot water until you reach a total volume of 23-25 liters in your boil kettle.

## STEP 5

**BOIL** - Start heating until you reach a boil and let simmer.

The hops shall boil for 60 minutes. Do not use lid!

Open the bag labeled **35 g Perle**. Pour the content into the kettle. Boil for 60 minutes.

Turn off the heat / Flame out!

## STEP 6

**COOLING** – Cool the wort as rapidly as possible to +20°C. Use spiral cooler or other cooling equipment. If you do not have any, put the fermentation bucket in a cool water bath.

**NOTE! Do not use any un-sanitized equipment or hands in the wort at this point.**

Take a sample and measure Oeschle value with a hydrometer and write down the result. This is the OG value.

## STEP 7

**FERMENTATION** – Open up the yeast package with a sterilized scissors and pour it into the cooled wort. Fill the airlock and put it into the lid of the fermentation bucket. Place the bucket on a spot keeping a temperature of +8-14°C.

The fermentation is normally done within 2-7 days. But let it be for 14 days.

When the fermentation is done take a wort sample and measure it with your hydrometer. This is the FG.

**Calculation ABV:**  $(OG-FG) \times 131,25 = ABV$

## BOTTLING

### SOME TIPS:

- ◆ Wash and sanitize the bottles. Put the caps in a bowl with sanitizer.
- ◆ We recommend **Carbonation Drops**. Follow the dosage instructions on the package. You can also use regular table sugar: 2-3 grams per 33 cl bottle.
- ◆ Fill the bottles with beer and leave a airpocket at the top. Cap it and place it in room temperature for at least one week. Open a bottle and test the carbonation levels. If you think its enough, chill for a week or two. Enjoy!