




RASPBERRY SOUR 20 LITER

SOUR



RASPBERRY SOUR

KIT CONTENT:

MALT:

2.7 kg BEST NP Ultra Pale Malt
1.5 kg BEST Wheat Malt

HOPS: 35 g Hüll Melon

PURÉE:

1 kg Raspberry Purée

YEAST:

1 pcs Philly Sour

EXPECTED OG: 1.048

EXPECTED FG: 1.012

EXPECTED ABV: 4.7 %

FERMENTATION TEMPERATURE: 25°C

MASH TEMP: 65°C

BOIL TIME: 60 min

HOP ADDITION TIMES: Hüll Melon 35 g - 5 min

BEER XML FILE: If you use an app like Brewfather you can download a XML file for this recipe under the product on maltmagnus.se

IF YOU HAVE BREWED BEFORE:

This is basic step-by-step instructions mainly for beginners. If you have brewed before, just use your brewing equipment as usual. You find mash temperatures and hop additions above.

YOU NEED:

- Cleaner and sanitizer
- Kettle or brewing equipment to boil 25-29 liters of wort.
- Kettle for heating sparge water.
- All Grain brewing equipment.
- Fermentation equipment.
- Bottling or kegging equipment.

Equipment and ingredients can be found at www.maltmagnus.se

BREW DAY

1. Start with making sure everything in the kit is included.
2. Read through the instructions!
3. Wash and clean the brewing equipment. Do not use the same equipment used while cooking or washing up.
4. Sterilize the equipment that will be in contact with the wort after chilling. Follow the dosage instructions on your sanitizer. Your beer can get infected if this step is not done correct.

STEP 1

1. Fill up with water to the false bottom if you have one before measuring 3 liters per 1 kg malt.
2. Heat the water to 65°C.

STEP 2

MASH IN - Add the crushed malt while stirring to avoid lumps. Mash at 65°C for 60 minutes.

STEP 3

MASH OUT - Rise the temperature while stirring to 76°C for about 10 minutes.

STEP 4

SPARGE - Prepare water in your hot liquor tank / kettle to a temperature of 80°C.

Rinse the malt gently with the hot water until you reach a total volume of 23-25 liters in your boil kettle.

STEP 5

BOIL - Start heating until you reach a boil.

The wort shall boil for 60 minutes. Do not use lid!

Boil for 55 minutes.

Open the bag labeled **35 g Hüll Melon**. Pour the content into the kettle. Boil for 5 more minutes.

Turn off the heat / Flame out!

STEP 6

COOLING – Cool the wort as rapidly as possible to around 25°C. Use spiral cooler or other cooling equipment. If you do not have any, put the fermentation bucket in a cool water bath.

NOTE! Do not use any un-sanitized equipment or hands in the wort at this point!

Take a sample and measure the Oeschle value with a hydrometer and write down the result.

This is the OG value.

STEP 7

FERMENTATION – Open up the yeast package with a sterilized scissor and pour it into the cooled wort.

Open up the package with purée and pour it into the cooled wort.

Fill the airlock and put it into the lid of the fermentation bucket.

Place the bucket on a dark spot keeping a temperature of around 25°C.

Leave for 14 days. When the fermentation is done take a wort sample and measure it with your hydrometer. This is the FG.

Calculation ABV: $(OG-FG) \times 131,25 = ABV$

BOTTLING

BOTTLING YOUR BEER:

1. Pour the finished beer into a keg.
2. If you want to carbonate in the bottle, you should add a new yeast, e.g. CBC-1 or similar, as Philly Sour is not suitable for carbonate fermentation.