

# SWBL IPA | 20 LITER

## IPA

#### YOU NEED:

- Cleaner and sanitizer
- Kettle or brewing equipment to boil 25-29 liters of wort.
- Kettle for heating sparge water.
- All Grain brewing equipment.
- Fermentation equipment.
- Bottling or kegging equipment.

Equipment and ingredients can be found at www.maltmagnus.se

## **BREW DAY**

Start with making sure everything in the kit is included.

Read through the instructions!

Take the yeast package out of the fridge.

Wash and clean the brewing equipment. Do not use the same equipment used while cooking or washing up.

Sterilize the equipment that will be in contact with the wort after chilling. Follow the dosage instructions on your sanitizer. Your beer can get infected if this step is not done correct.

## STEP 1

Heat 3 liters of water per 1 kg malt to +68°C. Fill up with water to the false bottom if you have one before measuring 3 liters per 1 kg malt.

We are very thankful for this collaboration where

Swedishbrewlady goes back to her roots and designed a recipe for us that reminds her of the early days when every new brew session felt like Christmas morning. And she hopes that when you try out this brew-kit you will have the very same experience, creating happy memories similar to hers.

## KIT CONTENT:

#### CRUSHED MALT:

3,0 kg Extra Pale Malt 2,0 kg Pilsner Malt | Svensk

#### HOPS:

15 g Amarillo 25 g Azacca 30 g Citra 20 g Citra 15 g Azacca

## YEAST:

1 Safale US-05

EXPECTED OG: 1.059

FERMENTATION TEMP: 15-22°C

#### ALREADY A SKILLED HOME BREWER:

Use your regular brewing equipment and brewing method. Time and temperatures can be found in this instructions.

STEP 2	STEP 6
MASH IN - Add the crushed malt while stirring. The temperature will now cool down a bit. Start heating again while stirring until you reach the correct temperature again Turn off the heat and put a lid on. Let rest for 90 minutes.         STEP 3         MASH OUT - Rise the temperature while stirring to +76°C for about 10 minutes.	<ul> <li>COOLING – Cool the wort as rapidly as possible to +23-25°C. Use spiral cooler or other cooling equipment. If you do not have any, put the fermentation bucket in a cool water bath.</li> <li>NOTE! Do not use any un-sanitized equipment or hands in the wort at this point.</li> <li>Take a sample and measure Oeschle value with a hydrometer and write down the result. This is the OG value.</li> </ul>
STED 4	
STEP 4 SPARGE - Prepare water in your hot liquor tank / kettle to a temperature of +80°C. Rinse the malt gently with the hot water until you reach a total volume of 23-25 liters in your boil kettle. STEP 5 BOIL - Start heating until you reach a boil and let sim- mer.	<b>STEP 7</b> <b>FERMENTATION</b> – Open up the yeast package with a sterilized scissors and pour it into the cooled wort. Fill the airlock and put it into the lid of the fermentation bucket. Place the bucket on a spot keeping a temperature of +15-22°C On the second day open the lid and pour the content of the bag labeled <b>20 g Citra</b> into the wort. This is callled dry hopping. The fermentation is normally done within 2-7 days. But let it be for 14 days. When the fermentation is done take a wort sample and measure it with your hydrometer. This is the FG. <b>Calculation ABV:</b> (OG-FG) x 131,25 = ABV
The hops shall boil for 60 minutes. Do not use lid!	
Open the bag labeled <b>15 g Amarillo</b> . Pour the content into the kettle. Boil for 45 minutes. Open the bag labeled <b>25 g Azacca</b> Pour the content into the kettle. Boil for 15 minuter. 60 minutes total boil time. Turn off the heat / Flame out! Open the bags labeled <b>30 g Citra</b> and <b>15 g Azacca</b> . Pour the content into the kettle and stir for a few minu- tes.	<ul> <li>BOTTLING</li> <li>SOME TIPS:</li> <li>Wash and sanitize the bottles. Put the caps in a bowl with sanitizer.</li> <li>We recommend Carbonation Drops. Follow the dosage instructions on the package. You can also use regular table sugar: 2-3 grams per 33 cl bottle.</li> <li>Fill the bottles with beer and leave a airpocket at the top. Cap it and place it in room temperature for at least one week. Open a bottle and test the carbonation levels. If you think its enough, chill for a week or two. Enjoy!</li> </ul>